

5.1.3.66. Open documents screen controller

Controller for the open documents screen (DEDOCCTR)

Organizational structure - Produmex Logex AddOn v18.2.1.41

Code: PMX_DEMO
Name: Produmex

General | Defaults | Extension parameters | Production | SSCC | Reports | Print events | Zone types | Page size | Q |

Property: Open documents screen controller (ODOCTRL)
Extension: Controller for the open documents screen (DEDOCCTR)
Search parameters:

Description	Value
Containers	
Order by (Container)	"ContainerType", "DocEntry"
View name (Container)	PMX_OPEN_DOCUMENT_REPORT_CONTAINER
Grid localization key (Container)	Logex.AddOn.OpenDocumentsReportForm.Grid.Container
Move orders	
Order by (Move order)	"DocEntry"
View name (Move order)	PMX_OPEN_DOCUMENT_REPORT_MOVE_ORDER
Grid localization key (Move order)	Logex.AddOn.OpenDocumentsReportForm.Grid.MoveOrde
Pick lists	
Order by (Pick list)	"WaveKey"
View name (Pick list)	PMX_OPEN_DOCUMENT_REPORT_PICKLIST
Grid localization key (Pick list)	Logex.AddOn.OpenDocumentsReportForm.Grid.PickList
Pick list proposals	
Order by (Proposal)	"DocEntry"
View name (Proposal)	PMX_OPEN_DOCUMENT_REPORT_PICKLIST_PROPO
Grid localization key (Proposal)	Logex.AddOn.OpenDocumentsReportForm.Grid.PickListPr
Pmx sales shipping	
Order by (Pmx sales shipping)	"DocEntry"
View name (Pmx sales shipping)	PMX_OPEN_DOCUMENT_REPORT_PMX_SALES_SHIP
Grid localization key (Pmx sales shipping)	Logex.AddOn.OpenDocumentsReportForm.Grid.PmxSales
Routes	
Order by (Route)	"DocEntry"
View name (Route)	PMX_OPEN_DOCUMENT_REPORT_ROUTE
Grid localization key (Route)	Logex.AddOn.OpenDocumentsReportForm.Grid.Route
Weigh orders	
Order by (Weigh order)	"DocEntry"
View name (Weigh order)	PMX_OPEN_DOCUMENT_REPORT_WEIGH_ORDER
Grid localization key (Weigh order)	Logex.AddOn.OpenDocumentsReportForm.Grid.WeighOrd

Ok Cancel Export Close

The settings below are to customize the grids shown on the open documents report.

There is a view to get the data to show on the grid. The order in which the columns are on the view, will also be the order in which they will appear in the grid.
Per view there are some mandatory fields, so the system knows what column to use for certain values.

Container

Order by - (Container)

The order by for the view. The text 'ORDER BY' does not need to be entered here.

View name - (Container)

The name of the view that will be used. Required fields:

- DocEntry

Grid localization key - (Container)

The localization key to use. This is used to translate the grid.

Move orders

Order by - (Move order)

The order by for the view. The text 'ORDER BY' does not need to be entered here.

View name - (Move order)

The name of the view that will be used. Required fields:

- DocEntry, FromPmxWhsCode, ToPmxWhsCode

Grid localization key - (Move order)

The localization key to use. This is used to translate the grid.

Pick lists

Order by - (Pick list)

The order by for the view. The text 'ORDER BY' does not need to be entered here.

View name - (Pick list)

The name of the view that will be used. Required fields:

- DocEntry, DestStorLocCode, WaveKey

Grid localization key - (Pick list)

The localization key to use. This is used to translate the grid.

Pick list proposals

Order by - (Pick list proposal)

The order by for the view. The text 'ORDER BY' does not need to be entered here.

View name - (Pick list proposal)

The name of the view that will be used. Required fields:

- DocEntry, DestStorLocCode, HasPickList

Grid localization key - (Pick list proposal)

The localization key to use. This is used to translate the grid.

Pmx Sales shipping

Order by - (Pmx sales shipping)

The order by for the view. The text 'ORDER BY' does not need to be entered here.

View name - (Pmx sales shipping)

The name of the view that will be used. Required fields:

- DocEntry

Grid localization key - (Pmx sales shipping)

The localization key to use. This is used to translate the grid.

Routes

Order by - (Route)

The order by for the view. The text 'ORDER BY' does not need to be entered here.

View name - (Route)

The name of the view that will be used. Required fields:

- DocEntry, LoadingDock

Grid localization key - (Route)

The localization key to use. This is used to translate the grid.

Below is a reduced translation tag for the standard grid is.

It shows how to translate, or if needed how to hide a columns.

```
<PmxLocalizationKey>
  <Canceled>False</Canceled>
<LocalizationKey>Logex.AddOn.OpenDocumentsReportForm.Grid.Route</Localizatio
```

```
nKey>
  <ApplicationTypeCode>SBOGUIAP</ApplicationTypeCode>
  <LocalizationProperties>
    <PmxLocalizationProperty>
      <Canceled>False</Canceled>
      <LocalizationProperty>Columns[1].HeaderText</LocalizationProperty>
      <ExtensionCode>CONVSTR</ExtensionCode>
      <LocalizationValues>
        <PmxLocalizationValue>
          <Canceled>False</Canceled>
          <LocalizationValue>Document number</LocalizationValue>
          <LanguageCode>3</LanguageCode>
        </PmxLocalizationValue>
        <PmxLocalizationValue>
          <Canceled>False</Canceled>
          <LocalizationValue>Type</LocalizationValue>
          <LanguageCode>16</LanguageCode>
        </PmxLocalizationValue>
      </LocalizationValues>
    </PmxLocalizationProperty>
    <PmxLocalizationProperty>
      <Canceled>False</Canceled>
      <LocalizationProperty>Columns[13].Visible</LocalizationProperty>
      <ExtensionCode>CONVB00L</ExtensionCode>
      <LocalizationValues>
        <PmxLocalizationValue>
          <Canceled>False</Canceled>
          <LocalizationValue>False</LocalizationValue>
          <LanguageCode>3</LanguageCode>
        </PmxLocalizationValue>
        <PmxLocalizationValue>
          <Canceled>False</Canceled>
          <LocalizationValue>False</LocalizationValue>
          <LanguageCode>16</LanguageCode>
        </PmxLocalizationValue>
      </LocalizationValues>
    </PmxLocalizationProperty>
  </LocalizationProperties>
</PmxLocalizationKey>
```

Weigh orders

Order by - (Weigh orders)

The order by for the view. The text 'ORDER BY' does not need to be entered here.

View name - (Weigh orders)

The name of the view that will be used. Required fields:

- DocEntry

Grid localization key - (Weigh orders)

The localization key to use. This is used to translate the grid.

From:
<https://wiki.produmex.name/> - **Produmex**

Permanent link:
<https://wiki.produmex.name/doku.php?id=implementation:wms:opendocumentsscreencontroller&rev=1531927303>

Last update: **2018/07/18 15:21**

