

3.2.3.2. Produmex pick list types (PMX_PLTY)

Pick list types are used on proposals and pick lists.

On a business partner there is also a default pick list type.

On a sales order/sales reserve invoice/warehouse transfer request a pick list type can be defined.

When creating a proposal, the system will set the pick list type in this order:

- Pick list type on document
- Pick list type on business partner (*Only for sales proposals*)
- Default pick list type

Configuration:

Code

The code.

Name

The name.

Split PL on item pick type?

When this is true, several pick list proposals can be created, grouping items with the same item pick type.

Split PL on item pick type 2?

When this is true, several pick list proposals can be created, grouping items with the same item pick type 2.

Ask weight?

When this is true, the weight of the (master) logistic unit will be asked when the logistic unit is finished. The data will be stored on the PMX_LUID table. The unit of measure is the Default Weight UoM set on the Display tab of General Settings.

Ask length?

When this is true, the length of the (master) logistic unit will be asked when the logistic unit is finished. The data will be stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.

Ask width?

When this is true, the width of the (master) logistic unit will be asked when the logistic unit is finished. The data will be stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.

Ask height?

When this is true, the height of the (master) logistic unit will be asked when the logistic unit is finished. The data will be stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.

Full pallet pick list type

When this is set, the proposal that is created will be split up between full quantity (*This is a multiple of the default quantity defined on the item master data*) and partial quantity (*Item pick*). The proposal created for the full pallet will have this pick list type.

Item pick pick list type

When this is set, the proposal that is created will be split up between full quantity (*This is a multiple of the default quantity defined on the item master data*) and partial quantity (*Item pick*). The proposal created for the item pick will have this pick list type.

Always status picked?

When this is true, the pick list line status after picking will always be 'Picked'. This means that when you pick without a moveable location, the status will not be 'Packed'. Pick lists with a type that have this setting, need to go through the 'Consolidated packing flow'. If any pick list within the same wave has this option, all pickings will follow this setting.

Use for production?

When this is true, the pick list can be used for pick lists of type 'Production'. When this is false, the pick list type can be used for shipping and warehouse transfer.

Use for picking?

When this is true, the pick list can be used in the picking flow.

At least 1 of the pick lists in the flow needs to have a pick list type with this flag enabled.

Use for ad hoc picking?

When this is true, the pick list can be used in the ad hoc picking flow.

Use for zone picking?

When this is true, the pick list can be used in the zone picking flow.

At least 1 of the pick lists in the flow needs to have a pick list type with this flag enabled.

Use for multi picking?

When this is true, the pick list can be used in the multi picking flow.

Number of pallets

This defines the number of pallets that can be added to a pick list proposal.

When the value is higher than 0, the proposals will be split during creation.

The splitting will be done based on the setting on the item master data for the default quantity on a logistic unit. (*OITM.U_PMX_DQLU*)

The system will calculate a fill rate of the proposal line, based on this setting. The fill rate of the proposal lines can go up to the defined number of pallets.

In case the default quantity on a logistic unit on the item master data is not set (=0), the fill rate of that proposal line will be 0.

Ask weight Sub SSCC?

When this is true, the weight of the logistic unit will be asked when the sub logistic unit is finished.

The data will be stored on the PMX_LUID table. The unit of measure is the Default Weight UoM set on the Display tab of General Settings.

Ask length Sub SSCC?

When this is true, the length of the logistic unit will be asked when the sub logistic unit is finished. The

data will be stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.

Ask width Sub SSCC?

When this is true, the width of the logistic unit will be asked when the sub logistic unit is finished. The data will be stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the

Display tab of General Settings.

Ask height Sub SSCC?

When this is true, the height of the logistic unit will be asked when the sub logistic unit is finished. The data will be stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.

Use for Cash register packing?

When this is true, the pick list can be used in the Cash register packing flow.

From:

<https://wiki.produmex.name/> - **Produmex**

Permanent link:

<https://wiki.produmex.name/doku.php?id=implementation:wms:plty&rev=1530278986>

Last update: **2018/06/29 13:29**

