


## 3.4. Packing line settings

On a packing line, items that have been picked on a movable location (picking cart) can be packed onto a logistic carrier to be shipped as a logistic unit with an SSCC.

Under the level of the packing line, a thin client element can be created directly (Mobile Client touchscreen mode).

### 3.4.1. General settings



#### **Active**

Set whether or not the packing line is active.

#### **Block stock from being used for the picking process**

If this setting is enabled, the stock on this location cannot be used to put on a proposal. Also when a pick list gets the allocation on location level, these locations are not taken in account.

The locations with this flag to true are added to the view PMX\_DISALLOWED\_LOCATIONS\_FOR\_PICKING

### 3.4.2. Cycle count

Organizational Structure - Produmex WMS Add-On

Search

Code: PL1  
Name: Packing Line 1

General Cycle Count

Cycle Counting **Location Not Counted Yet**

☐ Allow Location to Be Counted During Cycle Count  
☐ Allow Location to be Counted During Other Operations  
☐ Location Needs to Be Counted Now

Count After Number of Days: 0  
 Count After Number of Operations: 0  
 Locked By:

Unlock

Ok Cancel Inventory Close

### ***Allow location to be counted during cycle count***

Is the location allowed to be counted?

### ***Allow location to be counted during other operations***

Is the location allowed to be counted during other operations? This means that when this location is used on certain flows, the system will check if a count is needed. If so, the system will ask the user to perform a count.

### ***Locations needs to be counted now***

When this option is enabled, the location will be counted, regardless of the other settings (Number of days, number of operations, ...)

### ***Count after X days***

When a location has not been counted for the number of days defined here, the location needs to be counted. If the number is 0, this setting is not taken in account, and the setting on company level is taken.

### ***Count after X operations***

If the number of operations since the last count exceeds the defined number of operations, the location needs to be counted. If the number is 0, this setting is not taken in account and the setting on company level is taken.

### ***Locked by (read-only field)***

This field shows the key of the user that is locking the location, because he needs to count the location or is currently in process to count the location.

When a location is locked, it cannot be used in other processes.

The location is released by clicking the 'unlock' button.

Stock on locked locations is not taken in account to create pick list (proposals).

From:

<https://wiki.produmex.name/> - **Produmex**

Permanent link:

<https://wiki.produmex.name/doku.php?id=implementation:wms:packingline>

Last update: **2021/04/22 08:54**

