
2025/08/08 18:17 1/1 2.2. Users

2.2. Users

Additional setting for users

It is possible to set the language in which the "thin client" application runs for each individual users. To do this select Administration → Setup → General → Users. A user-defined field "Language" has been added there to allow you to set the language code for the user in question. This language is used on the scanner/touchscreen when the user has logged on.

• It is also possible to assign a user to a PMX User Group. The available authorizations are defined in the UDT "PMX_UAUT" (User Authorizations Definitions Table) and can be linked to the PMX User Groups (UDT "PMX_USGR") through the UDT "PMX_UGAU" (Link Usergroup To Authorizations Table).



From:

https://wiki.produmex.name/ - Produmex

Permanent link:

https://wiki.produmex.name/doku.php?id=implementation:wms:users

Last update: 2025/05/21 06:22

