


### 2.3.29. Produmex picklist types (PMX\_PLTY)

Open the **Picklist types** table:

**Tools > Default Forms > PMX\_PLTY Produmex Picklist types**



Picklist types are used on picklist proposals and picklists and can affect the following:

- if it is split to multiple picklist proposals or not,
- which users are allowed to pick the pick list (see: [user picklist types](#)),
- in which flows it can be picked,
- whether certain dimensions should be added during packing.

**For the following Picklist workflows you must enable these settings in the Produmex Picklist types table:**

Picklist Type	Setting	Enable
Box Pick and Pack	Use for Picking?	Yes
Zone Box Picking	Use for Zone Picking?	Yes
Prepare carts	Use for multi picking?	Yes

When creating a proposal, the system determines the picklist type based on the following settings in the mentioned order:

1. Picklist type on document. The picklist type can be set on sales orders, sales invoices and warehouse transfer requests.
2. Picklist type on business partner. A default picklist type for sales documents can be set for business partners on the [Business Partner Master Data](#).
3. Default picklist type. The default picklist type is the '**Standard**' picklist type. Do not delete the '**Standard**' picklist type as it might lead to errors when creating picklist proposals.

Column	Description
Code	The code of the picklist type
Name	The name of the picklist type
Split PL on item pick type?	When this is true, several picklist proposals can be created, grouping items with the same item pick type.

Column	Description
Split PL on item pick type 2?	When this is true, several picklist proposals can be created, grouping items with the same item pick type 2.
Full pallet picklist type	When this is set, the created proposal is split up between full quantity (this is a multiple of the default quantity defined on the item master data) and partial quantity (Item pick). The proposal created for the full pallet have this picklist type.
Item pick picklist type	When this is set, the created proposal is split up between full quantity (this is a multiple of the default quantity defined on the item master data) and partial quantity (Item pick). The proposal created for the item pick have this picklist type.
Always status picked?	When this is true, the picklist line status after picking will always be <i>Picked</i> , that is, when you pick without a moveable location, the status will not be <i>Packed</i> . Picklists with a type that have this setting, need to go through the Consolidated Packing flow. If any picklist within the same wave has this option, all pickings will follow this setting.
Ask weight?	When this is true, the weight of the (master) logistic unit is asked when the logistic unit is finished. The data is stored on the PMX_LUID table. The unit of measure is the Default Weight UoM set on the Display tab of General Settings.
Ask length?	When this is true, the length of the (master) logistic unit is asked when the logistic unit is finished. The data is stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.
Ask width?	When this is true, the width of the (master) logistic unit is asked when the logistic unit is finished. The data is stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.
Ask height?	When this is true, the height of the (master) logistic unit is asked when the logistic unit is finished. The data is stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.
Use for production?	When this is true, the picklist can be used for picklists of type <i>Production</i> . When this is false, the picklist type can be used for shipping and warehouse transfer.
Use for Picking?	When this is true, the pick list can be used in the Picking flow. At least 1 of the picklists in the flow needs to have a picklist type with this flag enabled.
Use for Ad Hoc Picking?	When this is true, the picklist can be used in the Ad Hoc Picking flow.
Use for Zone Picking?	When this is true, the picklist can be used in the Zone Picking flow. At least 1 of the picklists in the flow needs to have a picklist type with this flag enabled.
Use for multi picking?	When this is true, the picklist can be used in the multi picking flow.
Number of pallets	This defines the number of pallets that can be added to a picklist proposal. When the value is higher than 0, the proposals are split during creation. The splitting is done based on the setting on the item master data for the default quantity on a logistic unit. ( <i>OITM.U_PMX_DQLU</i> ) The system calculates a fill rate of the proposal line, based on this setting. The fill rate of the proposal lines can go up to the defined number of pallets. In case the default quantity on a logistic unit on the item master data is not set (=0), the fill rate of that proposal line is 0.
Ask weight Sub SCCC?	When this is true, the weight of the logistic unit is asked when the sub logistic unit is finished. The data is stored on the PMX_LUID table. The unit of measure is the Default Weight UoM set on the Display tab of General Settings.
Ask height Sub SCCC?	When this is true, the height of the logistic unit is asked when the sub logistic unit is finished. The data is stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.
Ask width Sub SCCC?	When this is true, the width of the logistic unit is asked when the sub logistic unit is finished. The data is stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.

Column	Description
Ask length Sub SSCC?	When this is true, the length of the logistic unit is asked when the sub logistic unit is finished. The data is stored on the PMX_LUID table. The unit of measure is the Default Length UoM set on the Display tab of General Settings.
Use for Cash Register Packing?	When this is true, the picklist can be used in the Cash Register Packing flow.
Print after item picked	If <a href="#">print event 204 - Picking: after item is picked</a> is set on the <a href="#">Print Events</a> tab of the Organizational Structure, the print event applies to those picklist types where setting <i>Print after item picked</i> is set to true.
Num of PL per Wave	Number of picklist per wave: In this column you can add the maximum number of picklists of the given type that has to be grouped into a wave. For more information click <a href="#">here</a> .

From:  
<https://wiki.produmex.name/> - **Produmex**

Permanent link:  
<https://wiki.produmex.name/doku.php?id=implementation:wms:plty>

Last update: **2024/10/14 11:31**

